

System settings and queries



factory reset



Software version



Decoding library version

Communication settings



**USB HID



Serial output

Serial port baud rate setting



**9600bps



19200



115200

sound setting



** Mute on



Mute off



** Turn on startup sound



Turn off startup sound



** Turn on decoded sound



Turn off decoded sound



** Turn on the setting code sound



Turn off the setting code sound

Buzzer settings



** Buzzer IF tone



Buzzer low frequency sound



Buzzer high frequency sound

Reading mode



Manual mode



Continuous mode

End character setting



** Add ENTER



Add line break



Add TAB



No suffix

Illumination and aiming



conventional



Always bright



No lighting



conventional



Always bright



no target

Prefix and postfix settings



** Prohibit adding prefix



Allow adding prefix



Enter to modify prefix



** No suffixes are allowed



Allow adding suffix



Enter to modify the suffix



Exit to modify the prefix and suffix

Data code



0



1



2



3



4



5



6



7



8



9



A



B



C



D



E



F

Note: items with "*" are the default items